

## CCNP BCMSN Notes - VLAN Trunking Protocol

VTP modes: **Client** - Rely on VLAN information advertised by a server; no local configuration possible  
**Server** - Have full control over VLAN creation and modification for the VTP domain  
**Transparent** - Does not participate in VTP but will forward advertisements  
VTP advertisements:  
**Summary** - Sent every 300 seconds or whenever a change occurs  
**Subset** - Sent after a summary advertisement when a change occurs; these provide more detail to reflect the change that was made  
**Advertisement Request** - Issued by clients to request VLAN information  
**Pruning Request** - Sent from clients to servers to announce active VLANs; inactive VLANs may be pruned from the trunk  
VTP configuration:

```
-----  
Switch(config)# vtp mode {server | client | transparent}  
Switch(config)# vtp version {1 | 2}  
Switch(config)# vtp domain <domain>  
Switch(config)# vtp password <password>  
-----  
VTP pruning can be enabled with vtp pruning. Verification: show vtp status show vtp counters
```